


## FlexTk Server OEM Version

The FlexTk storage management server is a standalone software product providing a highly simplified, yet customizable interface and allowing one to easily transform any PC-Based hardware platform into an integrated storage management solution capable of fully-automatically managing files on multiple network-attached servers, NAS devices and enterprise storage systems.

In order to simplify integration of the FlexTk server with OEM storage devices and enterprise storage systems, Flexense provides a special OEM version of the FlexTk server, which is allowing one to customize the vendor and product branding information across the entire web-based GUI interface.



The OEM version of the FlexTk server provides the user with the ability to control the company name and logo, company web site, product name and logo displayed on the header and title of all web pages, the server login dialog and the about dialog.

In order to specify custom vendor and product branding information, the user should edit the 'oem.xml' file located in the '<Product Root>\httpd' directory according to an open XML-Based format specified below, copy custom OEM company logo and product logo files to the same directory and restart the FlexTk server.

Note: Customizations explained in this document are applicable to the OEM version of the FlexTk Server only and will not work with the end-user product version. In order to obtain the OEM version of the FlexTk Server please contact: [support@flexense.com](mailto:support@flexense.com)

## FlexTk Server OEM Branding XML File Format

In order to specify custom vendor and product branding information, edit the 'oem.xml' file located in the '<Product Root>\httpd' directory according to the following XML format:

```
<oem>

    <company-name>OEM Company Name</company-name>
    <company-logo>oem_company_logo_200x50.jpg</company-logo>
    <company-url>http://www.oemcompany.com</company-url>

    <product-name>OEM Product</product-name>
    <product-logo>oem_product_logo_64x64.jpg</product-logo>

</oem>
```

Field	Description
<b>company-name</b>	Specifies the OEM company name that will be displayed under the OEM company logo in the top-right corner of all web pages.
<b>company-logo</b>	Specifies the OEM company logo image that will be displayed above the OEM company name in the top-right corner of all web pages. The logo image file (JPG, PNG, etc.) should be resized to the 200x50 pixels resolution and copied to the '<Product Root>/httpd' directory.
<b>company-url</b>	Specifies the OEM company web site URL that will be displayed on the server's about dialog under the OEM product name. In addition, the OEM company logo will point to the web address specified by this field.
<b>product-name</b>	Specifies the OEM product name that will be displayed beside the OEM product logo in the top-left corner of all web pages and on the server's about and login dialogs.
<b>product-logo</b>	Specifies the OEM product logo image that will be displayed beside the OEM product name in the top-left corner of all web pages and on the server's about and login dialogs. The logo image file (JPG, PNG, etc.) should be resized to the 64x64 pixels resolution and copied to the '<Product Root>/httpd' directory.

The OEM version of the FlexTk server reads the OEM branding XML file once during the server's startup and after that renders all web pages according to the specified information. In order to apply changes made to the OEM branding file, the FlexTk server should be restarted.

Note: Customizations explained in this document are applicable to the OEM version of the FlexTk Server only and will not work with the end-user product version. In order to obtain the OEM version of the FlexTk Server please contact: [support@flexense.com](mailto:support@flexense.com)